Nº	данные	LSB/	Формат	Обработка	
байта		MSB			
0	0хА5 (маркер)				
1	PMT_CURRENT	L	Без знака		
2		Н			
3	FLOW RATE	L	Без знака	Bias, coefficient > [9]Monitor flow	
4		Н			
5	PMT VOLTAGE	L	Без знака		
6		Н			
7	CONCENTRATION	L	Co	Описано в «Работа_Modbus_ТАБЛИЦА»	
8	(RAW)	Н	знаком		
9	AUX ADC#3	L	Без знака	Bias, coefficient> [12] Bypass pressure	
10	BYPASS PRESSURE	Н			
11	T (KELVIN)	L	Без знака		
12	ANALYTICAL CELL	Н			
13	T (KELVIN)	L	Без знака	Bias, coefficient> [13] Temp. of spectrometer	
14	SELF-TEST CELL	Н			
15	PRESSURE	L	Без знака		
16	ANALYTICAL CELL	Н			
17	AUX ADC#1	L	Без знака	Bias, coefficient> [10] Vacuum	
18	VACUUM	Н			
19	AUX ADC#2	L	Без знака	Bias, coefficient > [11] Dilution pressure	
20	DILUTION PRESSURE	Н			
21	STATUS				
22	CHECKSUM				

CHECKSUM – просто младший байт от суммы всех байтов посылки

СОДЕРЖАНИЕ БАЙТА СТАТУСА

BIT#	NAME	LEGEND	PIN#
0	reserved		
1	WATLOW 1 (INTERNAL)	1=OK 0=FAIL	X2:3
2	SELF-TEST CELL ON	1=OK 0=FAIL	
3	SELF-TEST CELL OFF	1=OK 0=FAIL	
4	WATLOW 2 (SAMPLE)	1=OK 0=FAIL	X2:4
5	WATLOW 3 (PROBE)	1=OK 0=FAIL	X3:3
6	WATLOW 4 (FILTER)	1=OK 0=FAIL	X3:4
7	WATLOW 5 (CONVERTER)	1=OK 0=FAIL	X4:3